

Warehouse Bin Locations

Warehouse bin locations can be entered in the system for products using various programs as described below. Primary and secondary locations can be entered. Then the primary location is printed on pick tickets and various reports.

The BAR menu contains a menu option that can be used to print bar code labels for the Product Shelves using Unform and a Zebra printer.

There are 6 menu options where bin locations can be entered/changed/removed. Each of these should be previewed to see which ones works most efficiently to update these based upon whether the operator is adding new locations or changing locations or entering secondary locations, etc.

- PMM Product Maintenance
- PMM Maintain Product Costs/Locations
- INV Add/Remove Locations
- BAR Add locations
- BAR Remove locations
- PYE Enter Inventory Cards

The primary location prints on pick ticket and the P.O. Receiving Report. Various reports can be printed by the primary location:

- PYE Inventory Count Forms
- PYE Physical Inventory Discrepancy Report
- INC Physical Count Report
- INC Product Cycle Count Report
- INV Count Discrepancy Report
- INV Count vs Re-Count Report

The following shows each of the options where bin locations can be entered and gives a sample screen shot. See the Harvest Documentation for a complete description of these and samples of the reports.

PRODUCT MAINTENANCE

The 3rd screen of Product Maintenance shows the primary location and the first few secondary locations. If there are more locations, then this is indicated with a plus sign (+) after the locations. This menu option allows the operator to change the primary location only.

FOR WALDEN SERVICES, INC

PART #: 62333303386
 ACB 1 LIGHT BULB

| | | |
|---------------------------|------------|--|
| TOTAL ON HAND: | 6,150 | 26. DETAIL STATUS CODE: 01 - STOCK ITEMS |
| QUANTITY PUT-UP: | 5,766 | 27. LOCATION: YARD A12345 TEST1 + |
| AVAILABLE TO PUT-UP: | 384 | |
| OPEN TO SELL, ON HAND: | 40,556- | ---- PURCHASING INFORMATION ---- |
| OPEN TO SELL, PO/WORK: | 8,706- | 28. USAGE RATE PER MONTH: 3 |
| OPEN TO SELL, PO/TR'S: | 8,706- | 29. LEAD TIME (in months): 2.00 |
| QTY DUE TO CUSTOMERS | 40,940 | 30. ORDER POINT: 1 |
| DIRECT SHIP TO CUST: | 12,320 | 31. LINE POINT: 9 |
| QTY DUE FROM PO'S: | 31,850 | 32. EOQ: 924 |
| QTY DUE TO TRANSFER: | 0 | 33. PURCHASE INFO LOCK: XX |
| QTY DUE FROM TRANSFER: | 0 | 34. AVERAGE ON-HAND QTY: 8,428 |
| | | 35. INVENTORY CLASS: 01 |
| STOCK \$ ON HAND: | 602,460.15 | VENDOR REVIEW CYCLE: .5 |
| DATE DETAIL ENTERED: | 12/11/2006 | CURRENT STOCKOUT BEGAN: 03/25/2010 |
| DATE LAST CUSTOMER ORDER: | 09/04/2012 | |
| EOQ TURNS: | 0.1 | |

OPTIONS: (AB, CR, LC, LT, PO, PR, PU, RE, S#, TK, TR, UP, ##, ?): ___

MAINTAIN PRODUCT COSTS/LOCATIONS

This menu option allows the operator to change Weighted Average Cost and/or Last Cost Paid and/or the primary location and up to 3 overstock locations.

12/12/12 PRODUCT COST CHANGE
 PRCSCH WALDEN SERVICES, INC

ITEM #: 62333303386_ACB 1 LIGHT U/M: E - EACH
 BULB

| | | | |
|---------------------------|--------|--------------------|--------|
| 1. WEIGHTED AVERAGE COST: | 97.961 | TOTAL ON HAND: | 6,150 |
| 2. LAST COST PAID: | 29.77 | RESERVED FOR SHIP: | 5,766 |
| 3. PRIMARY LOCATION: | YARD | AVAIL TO SELL: | 384 |
| 4. OVERSTOCK LOC: | A12345 | DUE TO CUSTOMERS: | 40,940 |
| 5. OVERSTOCK LOC: | TEST1 | DUE FROM P.O.'S | 31,850 |
| 6. OVERSTOCK LOC: | TEST2 | TRANSFERS: | 0 |

-----WEIGHTED AVERAGE COSTS-----

| DATE | P.O.# | PREV/NEW QTY | PREV/NEW WAC | U | COST | FREIGHT | |
|------------|-------------|--------------|--------------|---|----------|---------|-------|
| INIT | | | | | | | |
| 09/06/2012 | 0015702-001 | 6,000 | 26.96 | | 2,938.00 | 0.00 | PAT |
| | | 150 | 97.96 | E | | | 6:11 |
| am | | | | | | | |
| 04/12/2012 | 0000244-001 | 6,256 | 27.39 | E | 0.00 | 0.00 | |
| | | 100 | 26.96 | E | | | 11:39 |
| pm | | | | | | | |
| 04/12/2012 | 0000244-001 | 5,756 | 29.77 | | 0.00 | 0.00 | |
| | | 500 | 27.39 | E | | | 11:39 |
| pm | | | | | | | |

OPTIONS: (AB, CR, LC, WC, UP, ##): ___

ADD OR REMOVE LOCATIONS

This menu option allows an operator to add or change the primary location and an unlimited number of secondary locations.

```
09/12/12                                ADD AND REMOVE LOCATIONS
BCLCTN

PART # 62333303386 ACB 1 LIGHT
      BULB

      PRIMARY LOCATION: YARD

      OVERSTOCK LOCATIONS                TO REMOVE A LOCATION ENTER
LOCATION NAME
      A12345      TEST1
      TEST2      TEST3
      TEST6      TESTA

LOCATION: _____                HIT THE SPACE BAR AND <ENTER>
                                   TO ADD PRIMARY LOCATION
                                   <F3> FOR NEW PART NUMBER
```

ADD LOCATIONS

This menu option was designed to be used with a bar code scanner. It can also be used with a terminal, but the screen will only use the upper left corner of the terminal. It allows an operator to scan or enter locations. After the part is scanned and the location label is scanned or entered, it prompts the operator to add this as a secondary location or allows entry of a "P" to indicate that this is the primary location.

```
ADD LOCATIONS  BCLCAD

PART #:62333303386

MFG: ACB

CAT: 1 LIGHT

DESC: BULB

LOCATION: NEWABC_____

ADD? (Y/N/P)
```

REMOVE LOCATIONS

This menu option was designed to be used with a bar code scanner. It can also be used with a terminal, but the screen will only use the upper left corner of the terminal. It allows an operator to scan or enter locations. After the part is scanned and the location label is scanned or entered, it prompts the operator to remove this location. If the operator scans or enters a location that is not currently in the file for the item, the system indicates this and returns to the part # prompt.

```
REMOVE LOCATIONS  BCLCRM  
  
PART #:62333303386  
  
MFG: ACB  
  
CAT: 1 LIGHT  
  
DESC: BULB  
  
LOCATION: TESTA_____
```

REMOVE? (Y/N)

ENTER INVENTORY CARDS

This menu option is used as part of the procedures to do an annual inventory counter of the warehouse. As counts are entered, the operator can also enter the primary location of items. After the option is selected from the menu, the system prompts whether the operator would like to enter primary locations. If they indicate that they would, then the primary location is displayed for each item and the operator can change it. after they enter the inventory count for the item.

```
09/12/12          ENTER  INVENTORY  CARDS  
PYINCD
```


